


## - Configuring Static Routes -

### Configuring Static Routes

The basic syntax for a static route is as follows:

```
Router(config)# ip route [destination_network] [subnet_mask] [next-hop]
```

Consider the following example:



RouterA will have the 172.16.0.0/16 and 172.17.0.0/16 networks in its routing table as directly-connected routes. To add a static route on RouterA, pointing to the 172.18.0.0/16 network off of RouterB:

```
RouterA(config)# ip route 172.18.0.0 255.255.0.0 172.17.1.2
```

Notice that we point to the IP address on RouterB's fa0/0 interface as the *next-hop* address. Likewise, to add a static route on RouterB, pointing to the 172.16.0.0/16 network off of RouterA:

```
RouterB(config)# ip route 172.16.0.0 255.255.0.0 172.17.1.1
```

To remove a static route, simply type *no* in front of it:

```
RouterA(config)# no ip route 172.18.0.0 255.255.0.0 172.17.1.2
```

On point-to-point links, an **exit-interface** can be specified instead of a next-hop address. Still using the previous diagram as an example:

```
RouterA(config)# ip route 172.18.0.0 255.255.0.0 fa0/1
```

```
RouterB(config)# ip route 172.16.0.0 255.255.0.0 fa0/0
```

A static route using an exit-interface has an Administrative Distance of **0**, as opposed to the default AD of **1** for static routes. An exit-interface is only functional on a point-to-point link, as there is only one possible next-hop device.

\*\*\*

All original material copyright © 2007 by Aaron Balchunas ([aaron@routeralley.com](mailto:aaron@routeralley.com)), unless otherwise noted. All other material copyright © of their respective owners.

This material may be copied and used freely, but may not be altered or sold without the expressed written consent of the owner of the above copyright. Updated material may be found at <http://www.routeralley.com>.

### Advanced Static Routes Parameters

The Administrative Distance of a static route can be changed to form a **floating static route**, which will only be used if there are no other routes with a lesser AD in the routing table. A floating static route is often used as a *backup* route to a dynamic routing protocol.

To change the Administrative Distance of a static route to 250:

```
RouterA(config)# ip route 172.18.0.0 255.255.0.0 172.17.1.2 250
```

Static routes will only remain in the routing table as long as the interface connecting to the next-hop router is up. To ensure a static route remains *permanently* in the routing table, even if the next-hop interface is down:

```
RouterA(config)# ip route 172.18.0.0 255.255.0.0 172.17.1.2 permanent
```

Static routes can additionally be used to *discard* traffic to specific networks, by directing that traffic to a virtual *null* interface:

```
RouterA(config)# ip route 10.0.0.0 255.0.0.0 null0
```

### Default Routes

Normally, if a specific route to a particular network does not exist, a router will drop all traffic destined to that network.

A **default route**, or **gateway of last resort**, allows traffic to be forwarded, even without a specific route to a particular network.

The default route is identified by all zeros in both the network and subnet mask (*0.0.0.0 0.0.0.0*). It is the *least* specific route possible, and thus will *only* be used if a more specific route does not exist (hence “gateway of last resort”).

To configure a default route:

```
RouterA(config)# ip route 0.0.0.0 0.0.0.0 172.17.1.2
```

Advanced default routing is covered in great detail in another guide.

\* \* \*

All original material copyright © 2007 by Aaron Balchunas ([aaron@routeralley.com](mailto:aaron@routeralley.com)), unless otherwise noted. All other material copyright © of their respective owners.

This material may be copied and used freely, but may not be altered or sold without the expressed written consent of the owner of the above copyright. Updated material may be found at <http://www.routeralley.com>.